

**Arm® 926-EJS**  
**32-bit Microcontroller**

**N9H30**  
**Meter HMI**  
**User Manual**

*The information described in this document is the exclusive intellectual property of Nuvoton Technology Corporation and shall not be reproduced without permission from Nuvoton.*

*Nuvoton is providing this document only for reference purposes of NuMicro microcontroller based system design. Nuvoton assumes no responsibility for errors or omissions.*

*All data and specifications are subject to change without notice.*

For additional information or questions, please contact: Nuvoton Technology Corporation.

[www.nuvoton.com](http://www.nuvoton.com)

Table of Contents

1 OVERVIEW ..... 3

2 FEATURES ..... 4

    2.1 Meter HMI Features ..... 4

3 INSTALLATION AND ENVIRONMENT ..... 5

    3.1 Installing N9H30 Non-OS BSP..... 5

    3.2 Installing Meter HMI ..... 5

    3.3 System Requirements ..... 6

4 FOLDER STRUCTURE..... 7

    4.1 Meter HMI Folder Structure ..... 7

5 DESIGN GUIDE ..... 8

    5.1 Meter HMI ..... 8

    5.2 The Rotation of Needle..... 10

    5.3 Meter Operation..... 11

6 REVISION HISTORY ..... 14

## 1 OVERVIEW

Meter HMI for N9H30 is a GUI reference implementation.

This document utilizes Nuvoton N9H30 series general-purpose microprocessor N9H30F61IEC to implement Meter HMI with emWin GUI library. Nuvoton emWin GUI library supports hardware JPEG, BitBLT and OSD.




Figure 1-1 Meter HMI Main Menu

## 2 FEATURES

### 2.1 Meter HMI Features

- Support Nuvoton MPU N9H30
- Supports hardware JPEG decoder for baseline decoding
- Supports hardware BitBLT rotation and OSD overlapping
- Supports high quality and contrast LCD panel with resolution up to 800 x 480
- Supports SEGGER licensed emWin GUI library
- Supports many popular image formats, e. g., PNG, GIF, JPG and BMP
- Supports user defined image as icon source



Figure 2-1 Meter HMI Vehicle Speed

### 3 INSTALLATION AND ENVIRONMENT

#### 3.1 Installing N9H30 Non-OS BSP

First, download the latest N9H30 Non-OS BSP from [https://github.com/OpenNuvoton/N9H30\\_emWin\\_NonOS-master.zip](https://github.com/OpenNuvoton/N9H30_emWin_NonOS-master.zip) and unzip “N9H30\_emWin\_NonOS-master.zip” to a working folder, e. g., unzip it to the path “C:\N9H30”, where “N9H30” is the working folder.




Figure 3-1 N9H30 Folder

#### 3.2 Installing Meter HMI

First, download and unzip the latest “N9H\_emWin\_Template-master.zip” from [https://github.com/OpenNuvoton/N9H\\_emWin\\_Template](https://github.com/OpenNuvoton/N9H_emWin_Template) and copy “Meter\_N9H30\_NonOS” to the N9H30 sample path “C:\N9H30\N9H30\_emWin\_NonOS-master\BSP\SampleCode”.

Then, open KEIL project file at “C:\N9H30\N9H30\_emWin\_NonOS-master\BSP\SampleCode\Meter\_N9H30\_NonOS\KEIL\Meter\_N9H30\_NonOS.uvproj”, select the build option “Meter\_N9H30\_NonOS” and start compiling. The executable binary file is in “C:\N9H30\N9H30\_emWin\_NonOS-master\BSP\SampleCode\Meter\_N9H30\_NonOS\Bin”, called “Meter\_N9H30\_NonOS.bin”. Next, set USB booting of N9H30 board, connect the USB cable between PC/NB and N9H30, then power on N9H30. Run Windows tool NuWriter to burn the binary code into DDR/SRAM of board to test as follows.




Figure 3-2 NuWriter

As to burn the code into NAND, please refer to the document “Nuvoton N9H30 Platform\_Burn\_Code.pdf” or “NUC970 N9H30 NuWriter User Manual.pdf” for more details.

### 3.3 System Requirements

- KEIL IDE V5.xx and above with professional license
- Nuvoton N9H30 800 x 480 demo board (NuDesign HMI-N9H30 + NuDesign TFT-LCD7)

## 4 FOLDER STRUCTURE

### 4.1 Meter HMI Folder Structure

The content of “Meter\_N9H30\_NonOS” is described as follows.

Folder	Description
Meter_N9H30_NonOS	Base folder <ul style="list-style-type: none"> <li>● Meter_Reference_Implementation.pdf is user manual</li> <li>● main.c is for Meter HMI main entry</li> </ul>
Application	HMI folder <ul style="list-style-type: none"> <li>● GUIDemo.c is for Meter HMI image and data processing</li> <li>● Images.c is the C source code including all bitmap files</li> <li>● LCDConf2.c is for emWin display driver control</li> </ul>
Bin	Post built binaries folder <ul style="list-style-type: none"> <li>● Meter_N9H30_NonOS.bin is for Meter HMI execution file</li> </ul>
Photo	Resource folder <ul style="list-style-type: none"> <li>● All bitmap files for Meter HMI</li> </ul>
KEIL	Arm Keil MDK project folder
ThirdParty\emWin\Config	<ul style="list-style-type: none"> <li>● GUIConf.c is for emWin memory pool</li> </ul>

Table 4-1 Meter HMI Folder Structure

## 5 DESIGN GUIDE

Meter HMI reference implementation guide assumes that you already have a mature knowledge of the following:

- IDE operation for editing and compiling
- The C programming language, how to use linker and C compiler
- The N9H30 Non-OS BSP programming knowledge
- The basic emWin programming knowledge

**Note:** the basic Meter HMI utilizes SEGGER's emWin GUI library. About SEGGER's emWin GUI library user manual can be found at "C:\N9H30\N9H30\_emWin\_NonOS-master\ThirdParty\emWin\Doc\UM03001\_emWin.pdf".

### 5.1 Meter HMI




Figure 5-1 Meter HMI Control

Meter HMI offers anti-aliasing and high resolution approach drawing text and bitmap operations. Using Memory Device API to process degree rotation of bitmap needle, two memory devices operation and LCD display.

The background image of 800x480 is the file "Cluster\_back\_4.png" shown as follows





Figure 5-2 Background image of Meter HMI

If we update the changed image by using the 800x480 background image, the performance is very poor. So we use the trick to promote as follows.




Figure 5-3 Four Rectangles

In file GUIDemo.c, we create four memory devices for four rectangles, the representation is the coordinates ( left, top) and width X height, So rectangle D is (0, 0) and 800 X 480. Rectangle A is for the file FIG4.png, the representation is (208, 136) and 258 X 296, Rectangle B is for file FIG5.png, the representation is (208, 48) and 288 X 240, Rectangle C is for the file FIG6.png, and the representation is (304, 408) and 288 X 240, we use tool BmpCvtNuvoton to exports C files for PNG files. The following code create four memory devices to save the four bitmap files for rectangles, four memory devices for the result of rotation.

```

hScale = GUI_MEMDEV_CreateFixed32(0, 0, bmCluster_back_4.XSize,
bmCluster_back_4.YSize);

hScaleRot = GUI_MEMDEV_CreateFixed(0, 0, bmCluster_back_4.XSize,
bmCluster_back_4.YSize, GUI_MEMDEV_NOTRANS, GUI_MEMDEV_APILIST_32,
GUICC_M8888I);

hNeedle = GUI_MEMDEV_CreateFixed32(0, 0, _bmNeedle.XSize,
_bmNeedle.YSize);

hFIG4 = GUI_MEMDEV_CreateFixed32(0, 0, 258, 296);

hFIG4Rot = GUI_MEMDEV_CreateFixed(0, 0, 258, 296,
GUI_MEMDEV_NOTRANS, GUI_MEMDEV_APILIST_32, GUICC_M8888I);

hFIG5 = GUI_MEMDEV_CreateFixed32(0, 0, 288, 240);

hFIG5Rot = GUI_MEMDEV_CreateFixed(0, 0, 288, 240,
GUI_MEMDEV_NOTRANS, GUI_MEMDEV_APILIST_32, GUICC_M8888I);

hFIG6 = GUI_MEMDEV_CreateFixed32(0, 0, 288, 240);

hFIG6Rot = GUI_MEMDEV_CreateFixed(0, 0, 288, 240,
GUI_MEMDEV_NOTRANS, GUI_MEMDEV_APILIST_32, GUICC_M8888I);

```

## 5.2 The Rotation of Needle

The coordinates of needle is (400, 240), the center of rectangle D. We use tool BmpCvtNuvoton to open the file needle.png, counterclockwise rotation 90 degrees and export the C file as follows.




Figure 5-4 The needle of counterclockwise 90 degrees

The needle is located on X-axis of plane coordinates in mathematics, is also the location of 0 degree. The coordinates of circle center for the meter is (400, 240), the following code that needle rotates within the rectangle A.

```
static void _DrawFIG4Needle( int Angle, GUI_MEMDEV_Handle hDst) {
    int xSizeNeedle, ySizeNeedle, xSizeDst, ySizeDst;
    I32 SinHQ, CosHQ;
    //
    // Draw needle
    //
    xSizeNeedle = GUI_MEMDEV_GetXSize(hNeedle);
    ySizeNeedle = GUI_MEMDEV_GetYSize(hNeedle);
    xSizeDst = 384;    //440-28*2;
    ySizeDst = 208;    // 208;

    SinHQ = GUI__SinHQ((I32)((Angle) * (-1000)) + 90000);
    CosHQ = GUI__CosHQ((I32)((Angle) * (-1000)) + 90000);
    GUI_MEMDEV_RotateHQR(hNeedle, hDst,
        ((xSizeDst - xSizeNeedle) * 4) - (((xSizeNeedle)
        * CosHQ) >> 14),
        ((ySizeDst - ySizeNeedle) * 4) + (((xSizeNeedle)
        * SinHQ) >> 14
        (int)((Angle) * (-1000) + 270000), 1000);
}
.
```

How to obtain the values of variable “xSizeDst”, and “ySizeDst”? The coordinates (left, top) for rectangle A is (208, 136), so xSizeDst = (400 – 208) x 2 = 384, ySizeDst = (240 – 136) X 2 = 208. So the formula is xSizeDst = (X\_center – left ) X 2, ySizeDst = (Y\_center – top ) X 2. We could use the method for the needle rotation of other rectangles.

### 5.3 Meter Operation

The vehicle speed range is from 0 to 140. In the beginning set high resolution anti aliasing by the following code

```
// Initialize high resolution anti aliasing
GUI_AA_EnableHiRes();
```

```
GUI_AA_SetFactor(6);
```

Memory device “hScale” is for rectangle D, memory device “hScaleRot” is rectangle D with needle rotation. Memory device “hFIG4” is for rectangle A, memory device “hFIG4Rot” is for rectangle A with needle rotation. Memory device “hFIG5” is for rectangle B, memory device “hFIG5Rot” is for rectangle B with needle rotation. Memory device “hFIG6” is for rectangle C, memory device “hFIG6Rot” is for rectangle C with needle rotation. Memory device “hNeedle” is for needle.

we put 800 x 480 image that needle rotates 0 degree by the following code

```
speed = 0;
angle = speed *2;
GUI_MEMDEV_Select(hScaleRot);
GUI_Clear();
GUI_MEMDEV_Write(hScale);
_DrawSpeed(speed);
_DrawNeedle(angle, hScaleRot);
GUI_MEMDEV_CopyToLCD(hScaleRot);
GUI_MEMDEV_Select(0);
```

We set the following constant

```
#define T_MAX      6000    // 6 sec
#define MAX_SPEED  140
```

We could accelerate and brake the velocity by the following code

```
t0 = GUI_GetTime();
for (; (tDiff = GUI_GetTime() - t0) < T_MAX;) {
    tStart = GUI_GetTime();
    //
    // calculate speed dependent on time
    //
    if (tDiff < (T_MAX >> 1)) {
        f = 1 - (float)tDiff / (T_MAX >> 1);
        f = f* f;
        speed = MAX_SPEED - (MAX_SPEED * f);
    } else {
        f = 1 - ((float)tDiff - (T_MAX >> 1)) / (T_MAX >> 1);
```

```
f = f*f;

speed = (MAX_SPEED * f);

}

angle = speed*2;
```

The velocity has three conditional expression, the first is  $0 \leq \text{velocity} < 50$  for rectangle A, the second is  $50 \leq \text{velocity} < 90$  for rectangle B and the third is  $90 \leq \text{velocity} \leq 140$  for rectangle C. The following code is the operation of the first conditional expression for rectangle A.

```
if ((speed >= 0) && (speed < 50)) {

    GUI_MEMDEV_Select(hFIG4Rot);

    GUI_MEMDEV_WriteAt(hFIG4, 0, 0);

    _DrawFIG4Needle(angle, hFIG4Rot);

    _DrawFIG4Speed(speed);

    GUI_MEMDEV_CopyToLCDAt(hFIG4Rot, 208, 136);

}
```

We could run the needle rotation smoothly by the following code.

```
#define T_MIN_FRAME 35

tUsed = GUI_GetTime() - tStart;
if (tUsed < T_MIN_FRAME) {

    GUI_X_Delay(T_MIN_FRAME - tUsed);

}
```

In the file main.c, we use the function LCD\_Initial to set RGB565 for LCD as follows.

```
#ifdef _PANEL_FW070TFT_24BPP_

//    vpostSetVASrc(VA_SRC_RGB888);

    vpostSetVASrc(VA_SRC_RGB565);

#endif
```

It is better to set RGB565 instead of RGB888 for the performance.

It sets at least 7 MB memory for emWin GUI within the file GUIConf.c, otherwise the function fails to run.

```
#define GUI_NUMBYTES (1024 * 1024 * 7)
```

## 6 REVISION HISTORY

Date	Revision	Description
2022.1.28	1.00	1. Initially release.

### Important Notice

Nuvoton Products are neither intended nor warranted for usage in systems or equipment, any malfunction or failure of which may cause loss of human life, bodily injury or severe property damage. Such applications are deemed, "Insecure Usage".

Insecure usage includes, but is not limited to: equipment for surgical implementation, atomic energy control instruments, airplane or spaceship instruments, the control or operation of dynamic, brake or safety systems designed for vehicular use, traffic signal instruments, all types of safety devices, and other applications intended to support or sustain life.

All Insecure Usage shall be made at customer's risk, and in the event that third parties lay claims to Nuvoton as a result of customer's Insecure Usage, customer shall indemnify the damages and liabilities thus incurred by Nuvoton.

---

*Please note that all data and specifications are subject to change without notice.  
All the trademarks of products and companies mentioned in this datasheet belong to their respective owners.*